How to Conduct this Class

- Setup
  - AFATDS:
    - IMEF database loaded.
      - Do not implement Plan Volcanic

How to Conduct this Class

- Setup
  - SISTIM:
    - Not Required
  - Start class on next slide.





C2PC-EMT Setup

All MOS’S



Objective

- Load EMT Software
- Configure the C2PC Laptop for EMT Use
- Create an EMT User at AFATDS

Load EMT Software

- Insert EMT CDROM in PC CD drive.
- Click **Start, Run**
  - Browse to the CD and select **EMTsetup.exe**
  - Click **OK**

InstallAnywhere Starts

Wait for...


Effects Management Tools
Introduction
InstallAnywhere will guide you through the installation of your application. Use the "Next" button to proceed to the next screen. If you want to change something in a previous screen, click the "Previous" button. You may quit the installer at any time by clicking the "Exit" button.
InstallAnywhere by Zero G
Cancel
Previous
Next

Click Next...


Effects Management Tools
Choose Install Folder
Where Would You Like to Install?
C:\Program Files\EMT
Restore Default Folder
Choose...
InstallAnywhere by Zero G
Cancel
Previous
Next

Click Next...


Effects Management Tools
Choose Map Components for the tools
Install Set
All Components
C2PC Map
JMTK Map
AAS Emulator
Description
InstallAnywhere by Zero G
Cancel
Previous
Next

Click Next...


Effects Management Tools
Enable comms over radio?
Check the following box if you would like to install the software to enable comms over CNR:
Install CNR components
InstallAnywhere by Zero G
Cancel
Previous
Next

Click Install...



NOTE…

If EMT will be used only with C2PC and not as a standalone
application, the JMTK map may be de-selected and thus no
loaded. This saves considerable space on the hard drive o
The IOW.

Installation begins…



Wait for...


Effects Management Tools
Install Complete
Congratulations! The installation is complete. Press "Done" to quit the installer.
InstallAnywhere by Zero G
Cancel
Previous
Done

Click Done...


Effects Management Tools
Install Complete
Congratulations! The installation is complete. Press "Done" to quit the installer.
InstallAnywhere by Zero G
Cancel
Previous
Done

For Windows 2000 only...


BringToFront
Foreground Properties
Flash
5
Timeout
0
Enable for C2PC
Restore Backup
Restore Default
OK
Cancel
Help
This utility controls the number of times an application flashes on the taskbar when it requires attention and how long of a timeout before the application is brought to the foreground. The C2PC FSC application requires the ability to bring applications to the foreground. If this ability is not enabled, the user must manually select the flashing application from the taskbar.
This change will affect ALL installed applications.
Selecting "Enable for C2PC" will allow applications to come to the foreground immediately. "Restore Backup" will restore the settings that were in effect prior to enabling for C2PC. "Restore Default" will restore the Microsoft Windows 2000 default settings.
Click OK the save your changes or click CANCEL to discard any changes.

C2PC Client…

- Is now loaded
- If C2PC and AFATDS are on network, the client is now ready to operate.

If C2PC and AFATDS are not in the network...

The following steps apply only when the AFATDS
rator must setup a network communications between C2PC
AFATDS for training purposes.

At AFATDS…

- Create a LAN network in the current comm config
  - This may be the permanent LAN or any operator configured LAN

At C2PC...



Double-click Network

At C2PC...



Click on the Protocol Tab

Double-click TCP/IP Protocol

Set the IP address...


Microsoft TCP/IP Properties
IP Address
DNS
WINS Address
Routing
An IP address can be automatically assigned to this network card by a DHCP server. If your network does not have a DHCP server, ask your network administrator for an address, and then type it in the space below.
Adapter:
[1] Compaq Netelligent 10/100 PC Card
Obtain an IP address from a DHCP server
Specify an IP address
IP Address:
Subnet Mask:
Default Gateway:
Advanced...
OK
Cancel
Apply

Click Specify an IP Address

Type the IP Address and subnet mask. Enter the IP addres as the default gatew

Reboot if prompted!

At EMT, click **EMT, Utilities, Set AFATDS Info**



At AFATDS…

…establish client users.

Click **System, Administration, Client/User...**



Click the **NEW** icon



Create new Client
Client Name:
New Password:
Verify New Password:
OK
Cancel

Create User: ffc1imef with password:ffc1imef





Click on the **Login Permitted**

User appears in tree.

Automatically assigns default group

What if AFATDS server address changes?

- The client can be directed to a different server or a change in the server IP address.
- On the C2PC laptop, click **Start, Programs, EMT, Utilities, Set AFATDS info**

Host Editor Appears



Type AFATDS Hostname for th Network

Type AFATDS IP Address on the net shared by C2PC an AFATDS

Click OK

Confirm the change…



On Next Login…


COE Security Banner
Starting COE Security Banner
CreateService failed - The specified service already exists.
UNCLASSIFIED

COE Security Banner starts

Banner displays in front of any other window

Summary